

# POC TRANSITION TOOL RELEASE NOTES 18OCT17

Prepared By: AEMO

Version No: 0.1

Status: Draft

Date: 18 Oct 2017

## Document Control

### DOCUMENT DETAILS

DETAIL	VALUE
Document title	PoC Transition Tool Release Notes 18OCT17
Tool Version	V1.0.1 (PoCTransitionTool_201710171438_v1.0.1)
Document version	1
Document date	18 Oct 2017
Author	AEMO
Project	PoC Transition Tool Project
Distribution	Participants utilising PoC Transition Tool

### RELATED DOCUMENTS

FILE NAME	DOC REF	DESCRIPTION
None		

### DOCUMENT HISTORY

VERSION	FINAL EDIT DATE	AUTHOR(S)	CHANGES AND COMMENTS
0.1		AEMO	Initial Version



## Table of Contents

- 1. INTRODUCTION ..... 2
- 2. POC TRANSITION TOOL PROJECT SCOPE ..... 2
- 3. RELEASE TRACKING LIST ..... 3
  - 3.1 Release Notes ..... 3
  - 3.2 User Instructions ..... 3



## 1. Introduction

This document contains the Release Notes stating changes made to the PoCTransitionTool; released as part of version 1.0.1.

## 2. POC Transition Tool Project Scope

### Original Scope:

INT ITEM	APPLICATION	COMPONENTS	COMMENTS
1	PoCTransitionTool	Inbound Transformer	Used to transform Inbound r36 schema files to r32 schema.



### 3. Release Tracking List

#### 3.1 Release Notes

DATE	STATUS	APPLICATION	BUILD LABEL	RELEASE NOTES
18/10/17	Released	PoCTransitionTool Inbound Processing	v1.0.1	<p>'version' attribute related to the following XML elements is optional in r36 but is mandatory in r32</p> <ul style="list-style-type: none"> <li>AmendMeterRouteDetails</li> <li>AmendMeterRouteDetails -&gt; AmendSiteAccessDetails</li> <li>MeterDataNotification</li> <li>ServiceOrderResponse</li> </ul> <p>If the 'version' attribute is populated in 'r36', the tool transforms to the correct value of 'version' in r32. But if the 'version' attribute is not populated in 'r36' it does not default the value of 'version' in 'r32'. This creates an invalid transformed aseXML file.</p> <p>Additional Rule was implemented to fix the above problem statement :</p> <p>If the 'version' attribute in the following elements is not populated in 'r36' aseXML file</p> <ul style="list-style-type: none"> <li>AmendMeterRouteDetails Default it to 'r19' when transforming to 'r32' aseXML file</li> <li>AmendMeterRouteDetails -&gt; AmendSiteAccessDetails Default it to 'r19' when transforming to 'r32' aseXML file</li> <li>MeterDataNotification Default it to 'r25' when transforming to 'r32' aseXML file</li> <li>ServiceOrderResponse Default it to 'r17' when transforming to 'r32' aseXML file</li> </ul>

#### 3.2 User Instructions

- New Users

Please download the new version of the tool (v1.0.1) from AEMO website.

- Existing Users

If the Participants have already installed / configured the tool; please use the following instructions

- Stop running the tool



Release Tracking List

- Open PoCTransitionTool\_201710171438\_v1.0.1.zip
- Go to \PoCTransitionTool\B2B\lib
- Copy 'PoCTransitionTool.jar' from the above folder to the '/lib' folder where the tool is configured to run
- Restart the tool

- Participants requiring source code

AEMO will provide the updated source code to the Participants who have already requested / received the source code. The following Java files have been changed

- B2BInboundTransformer.java
- B2BExtension.java